

Singularity viewer

The Singularity Viewer is an OpenSimulator protocol compatible client application. It can be used to access OpenSim platforms. It needs to be set to the TILA Project grid.

Advantages

In this viewer the voice settings are already done. So it only needs to be installed and set to the TILA grid. It also has some extra features like 'web on a prim' and 'mesh' compatibility.

System requirements

After installing the viewer on your computer it checks if your computer has the requirements to run the software. So advised is to install it and see if your computer can run it.

Singularity has software for: WINDOWS (32-bit), Windows (64-bit), MAC OS X, Linux 32-bit and Linux 64-bit.

The official requirements are: a Dual-core CPU with SSE2 support, NVidia or ATI/AMD graphics chip, 2GB RAM, Windows XP or newer, Ubuntu Linux 10.04 or newer, Mac OS X 10.6 or newer. Other systems support pending.

Download


The Singularity viewer can be downloaded here: <http://www.singularityviewer.org/downloads>

Always do a clean install, so if there is an update, first uninstall the old version.

Viewer settings

To log in at the TILA Project grid you have to set the Singularity viewer to this grid.

- Start the viewer, click on the **GRID MANAGER** button at the bottom, see --->
- Click on the **CREATE** button (see below picture)




- Fill in the field **LOGIN URI** with: **tilaproject.eu:8002** or **http://tilaproject.eu:8002/**
- Click on **REFRESH GRID URLS**
- Click on **APPLY** at the right bottom
- Click on **DEFAULT** at the top (this sets the TILA grid as default grid)
- Finally click on **OK** at the bottom




- Fill in the **Username** (first and last name with a space between it) and **Password** fields with your personal data.
- (optional) Choose the **TILA Project grid** from the GRID list
- Click on **Log In**

Alternate look (Imprudence look)

If you want the viewer to look like the Imprudence viewer you can change that in the preferences.



- Click on the menu item **EDIT -> Preferences...**
- Select **SKIN** at the left side
- Click on the upper **SELECTED SKIN** and select **CLASSIC**
- Click on **OK** and RESTART the viewer



TIPS & TRICKS

- To be sure that no other grid can be selected, delete all other grids in the GRID MANAGER.
- Do **not select** the **REMEMBER PASSWORD** at the logging screen. Or else others can use your account
- If someone forgot their name or password: <http://tilaproject.eu:8002/wifi/forgotpassword>
- If textures are not showing and objects stay grey, go to **PREFERENCES -> NETWORK** then click the **CLEAR CACHE** button, and restart the viewer.